TrueBrew



DOUBLE IPA Ingredient Kit OG: 1.069-1.073

Ready: 2-4 weeks

Not for the faint of taste buds! A new American classic, brewed with 7 ounces of hops, hops, and more hops, and then balanced with a heavy dose of malt. Massive floral aroma and flavor, with serious bitterness.

Brew Date : Final Gravity :
Bottling Date :
Fermentation Temperature :
Notes:

INVENTORY

Specialty Grain Blend:

- 6 oz Crisp Crystal 60L (Step 2)
- Mesh steeping bag (Step 2)

Malts:

- 2 x 3.3 lb cans Light Liquid Malt Extract (Step 3)
- 1 x 1 lb Extra Light Dry Malt Extract (Step 3)

Yeast:

 11.5 g Fermentis US-05 Ale Yeast (Step 11)



Hops & Flavorings:

- 1 oz US Centennial Hop Pellets (Step 5)
- 1 oz US Willamette Hop Pellets (Step 6)
- 1 oz US Centennial Hop Pellets (Step 6)
- 1 oz US Amarillo® Hop Pellets (Step 6)
- 1 oz US Cascade Hop Pellets (Step 7)
- 1 oz US Amarillo® Hop Pellets (Step 13)
- 1 oz US Cascade Hop Pellets (Step 13)

Other:

- 5 oz Priming Sugar (Step 15)
- Instructions



LET'S BREW SOME BEER!

PREPARATION:

Before brew day, make sure you have the following:

- A homebrewing equipment kit for brewing 5 gallon batches for sanitizing, fermenting, and bottling
- A brew pot of at least 3.5 gallons capacity for boiling malt & hops with water
- Access to running water and a burner or stove for Brew Day
- A quiet, dark spot to keep the fermentor for Fermentation
- Approx. two cases of empty pry-off beer bottles for Bottling Day

BREW DAY

BREWING

1. Fill your brew pot with approximately 2.5 gallons of water, and begin heating it.



- 2. Pour the **Specialty Grain Blend** into the open end of the **mesh steeping bag**, then tie a knot in the open end. Steep the bag of specialty grain in the water as it heats, for approximately 15-20 minutes, then remove and discard the grain and bag.
- 3. Pour 2 cans of Light liquid malt extract and 1 bag Extra Light dry malt extract into the warm water in the brew pot and stir until dissolved.
- 4. Bring the malt-water mixture to a boil, and set a timer for 15 minutes.



5. When 15 minutes is up, add 1 oz of US Centennial hops to the brew pot and reset the timer for 30 minutes.



6. When 30 minutes is up, add 1 oz US Willamette hops, 1 oz US Centennial hops, and 1 oz US Amarillo® hops to the brew pot and reset the timer for 14 minutes.



- 7. When 14 minutes is up, add 1 oz US Cascade hops to the brew pot and boil for 1 more minute.
- 8. After 1 minute is up, turn off the heat the boil is now finished.

COOLING

- 9. Cool the malt-hop-water mixture (called "wort") with a wort chiller (if you have one) or by putting the covered brew pot in an ice bath until no longer warm to the touch.
- 10. Pour the cooled wort into a sanitized fermentor and add water to bring the volume up to 5 gallons.

FERMENTATION & DRY HOPS



- 11. Carefully cut open the pack of **Fermentis SafAle US-05 yeast** and sprinkle over the surface of the wort, then seal the fermentor and move to a quiet, dark location that is approximately 70°F.
 - 12. The yeast will convert malt sugars to alcohol and CO2 gas this will usually start within 24-48 hours of brew day and finish in about 7-10 days.



13. After the beer has fermented for 3 days, carefully open the fermentor and pour 1 oz US Amarillo® hops and 1 oz US Cascade hops into the fermenting beer. Re-seal the fermentor and continue with fermentation.

BOTTLING DAY

12. When fermentation is complete, sanitize your homebrew kit's siphoning and bottling equipment, as well as approximately 2 cases of pry-off bottles and enough bottlecaps to cap them.



- 13. Prepare a priming solution by mixing 5 oz priming sugar with 1 pint of boiling water.
- 14. Mix the priming solution with the fermented beer.
- 15. Fill the bottles with primed beer and cap.
- 16. Store the bottles in a dark place at 70°F for 10-14 days to carbonate.
- 17. Chill the bottles and enjoy your homemade hand-crafted Double IPA!

